



Nobel_V2.800.0000002.0.R.191225

Release Notes

ZHEJIANG DAHUA VISION TECHNOLOGY CO., LTD.

Legal Information

Copyright

© 2019 ZHEJIANG DAHUA VISION TECHNOLOGY CO., LTD. All rights reserved.

This document cannot be copied, transferred, distributed, or saved in any form without the prior written permission of Zhejiang Dahua Vision Technology Co., LTD (hereinafter referred to as "Dahua").

The products described in this document may contain the software that belongs to Dahua or the third party. Without the prior written approval of the corresponding party, any person cannot (including but not limited to) copy, distribute, amend, abstract, reverse compile, decode, reverse engineer, rent, transfer, sublicense the software.

Trademarks

 and **HDCVI** are the trademarks or registered trademarks of Dahua.

All other company names and trademarks mentioned herein are the properties of their respective owners.

Disclaimer

- These release notes are for reference only, and the actual product shall prevail.
- Succeeding products and release notes are subject to change without notice.
- If there is any uncertainty or controversy, please refer to our final explanation.

Table of Contents

Legal Information	I
Release Notes	1
1.1 Overview	1
1.2 New Features	1
1.3 Fixed Bugs	1
1.4 Compatibility.....	1
1.4.1 Program	1
1.4.2 Browser.....	1
1.4.3 Third Party Access.....	1
1.5 Software Environment.....	2
1.6 Pending Issues.....	2
1.7 Upgrade Guide.....	2

Release Notes

1.1 Overview

Item	Description
Product name	Nobel platform series
Version	V2.800.0000002.0.R. 191225
Software package information	DH_SD-Nobel_MultiLang_NP_Stream3_V2.800.0000002.0.R.191225.zip DH_SD-Nobel_MultiLang_PN_Stream3_V2.800.0000002.0.R.191225.zip
OS requirement	None
Release date	2020/1/20

1.2 New Features

First release.

1.3 Fixed Bugs

First release.

1.4 Compatibility

1.4.1 Program

First release. No compatibility issue.

1.4.2 Browser

IE9\IE10\IE11\Firefox\Chrome (Use Chrome under V42, and Firefox under V52).

Browser not supported: Chrome newer than Chrome 42, Firefox newer than Firefox 52, and win10-edge.

1.4.3 Third Party Access

- CGI testing tool version: V3.01.4
- ONVIF testing tool version: V17.12
- ONVIF: Supports ProfileG and Profile S
- MILESTONE: Supports Xprotect Corporate 2018, device pack 9.6a
- GENETEC: Supports Security Desk 5.7SR3

Error! Use the Home tab to apply 标题 1,1,1,H1,Title1,Normal + Font: Helvetica,Bold,Space Before 12 pt,Not Bold,Heading One,h1,Head1,Head,1,Numbered,nu,Level 1 Head,1st level,Section Head,Sec1,h11,1st level1,h12,1st level2,h13,1st level3,h14,1st level4,h15,1st level 1

1.5 Software Environment

Platform	Model	Version
Client	SmartPSS	DH_SMARTPSS-Win32_ChngEng_IS_V2.002.0000009.0.R.190426.zip
Tool	Player	General_SmartPlayer-Win32_ChngEng_IS_V4.000.0000000.5.F01.R.20180515.zip
	ConfigTool	General_ConfigTool_ChngEng_V4.011.0000003.5.R.20190722.zip
DSS	DSS-PRO	General_DSS-PRO_Win64_IS_V7.002.0000002.1.R.20190418.exe

1.6 Pending Issues

No.	Issue Description	Possible Result	How to Fix
1	For the scenes with multiple lights at night, when the camera is in large zoom, the image might not be clear after focusing.	Live view and capture might be affected.	New algorithm and functions have been incorporated in V2.800.0000003.0.R to fix this issue.

1.7 Upgrade Guide

This platform supports dual backup. Keep the power on during upgrading.

