

Leto_V2.680.0000000.2.R.190301

Release Notes

Disclaimer

- These release notes are for reference only, and the actual product shall prevail.
- Succeeding products and release notes are subject to change without notice.
- If there is any uncertainty or controversy, please refer to our final explanation.

Trademarks

All the company names and trademarks mentioned herein are the properties of their respective owners.

Table of Contents

Foreword	1
Release Notes	1
1.1 Overview	1
1.2 New Features	1
1.3 Fixed Bugs	1
1.4 Compatibility	1
1.4.1 Program	1
1.4.2 Browser	1
1.4.3 Third Party Access	1
1.5 Software Environment	2
1.6 Pending Issues	2
1.7 Update Guide	2

1.1 Overview

Item	Description
Product name	Leto platform series
Version	V2.680.0000000.2.R.190301
Software package information	EZIP_IPC-XXBXX-Leto_EngSpnPrt_N_V2.680.0000000.2.R.190301.zip EZIP_IPC-XXBXX-Leto_EngSpnPrt_P_V2.680.0000000.2.R.190301.zip General_IPC-HX2(1)XXX-Leto_EngSpnPrt_N_V2.680.0000000.2.R.190301.zip General_IPC-HX2(1)XXX-Leto_EngSpnPrt_P_V2.680.0000000.2.R.190301.zip
OS requirement	None
Release date	2019/3/31

1.2 New Features

Feature	Description
1	None

1.3 Fixed Bugs

After the upgrading caused by partition changes, web cannot be opened

1.4 Compatibility

1.4.1 Program

- For IPC-XXBXX, IPC-HX2(1)XXX, the programs are compatible with the previous release.
- Once update to this version(V2.680), you cannot change back to older version(V2.622)

1.4.2 Browser

IE9\IE10\IE11\Firefox\Chrome (Use Chrome under V42, and Firefox under V52)

1.4.3 Third Party Access

- ONVIF testing tool version: V18.06
- ONVIF: Supports ProfileS
- GENETEC testing tool version: Security Desk 5.7 SR2

1.5 Software Environment

Platform	Model	Version
NVR	NVR4208-8P-HDS2	General_NVR4XXX-4KS2_Eng_V3.216.0000000.0.R.180605.zip
	NVR5432-16P-4KS2	General_NVR5XXX-4KS2_Internal_V3.216.0000000.0.R.20180530
Client	SmartPSS	General_SmartPSS_ChnEng_Win32_IS_V2.02.0.R.171124.zip
	DMSS	IOS-Plus:V4.11.001 Android-Plus: V4.11.001
Tool	Player	General_Player_Eng_WIN32_V3.44.0.R.170421.zip
	ConfigTool	General_ConfigTool_ChnEng_V4.10.1.R.20180523
	PlaySDK	General_PlaySDK_Eng_Windows32_IS_V3.39.1.R.171130.zip
	NetSDK	General_NetSDK_Eng_Win32_IS_V3.48.2.R.170712.7z
DSS	DSS 7XXXS2	None

1.6 Pending Issues

No.	Issue description	Possible result	How to fix
1	Configure health e-mails with 60 s interval, and there might be wave during the intervals.	When checking the health e-mails, you might find that the interval is not the same with what you configured. If the configured interval is 60 s, usually the error is within 2 s, but in rare cases, the error might be 4 s.	No solutions at present.(You can reduce the error by shortening the interval of sending health e-mails, but that will cause the frequently sending of the health e-mails.)
2	Local record plan function is added on the new App, but it pops up configuration getting failed after clicking the function button.	It is the new added function on App, but the device does not supports the function synchronously, so the client cannot use the local record plan function.	You can use the local record plan on Web if it is necessary..
3	The update fail and need to reboot notice appears on one camera when 12 or more cameras doing update on the web interface at the same time.	None, the update will succeed.	Wait until the update is finished, and then refresh the web interface.

1.7 Update Guide

None